

# EL MODELO DE MAYO

Official NORTHERN BREWER Instructional Document

Built around a traditional Old World malt backbone that shows facets of caramel and chocolate, and suffused with balanced bitterness and understated noble hop character, Modelo Mayo pours deep red-amber with a white collar. But wait! The very non-Germanic inclusion of body-lightening dextrose and a hybrid yeast strain lets the drinker know that ya no estamos en Vienna, hijo. Brew for Cinco de Mayo, but stash a case away to partner with mole or Tex-Mex chili con carne all summer long.

**O.G: 1.050 READY: 6 WEEKS**

3-4 weeks primary, 2-3 weeks bottle conditioning

## KIT INVENTORY:

### MAILLARD MALTS™ SPECIALTY GRAIN

- 0.25 lbs Weyermann CaraAroma
- 0.25 lbs Weyermann Caramunich III
- 0.125 lbs Weyermann Dehusked Carafa I

### MAILLARD MALTS™ EXTRACTS & OTHER FERMENTABLES

- 5 lbs Amber DME (60 min)
- 1 lb Corn Sugar late addition (0 min)

### BOIL ADDITIONS

- 0.75 oz Perle (60 min)

### YEAST

- **WYEST 2124 BOHEMIAN LAGER.** Apparent attenuation: 73-77%. Flocculation: Medium-low. Optimum temp: 45-68° F.

### PRIMING SUGAR

- 5 oz Priming Sugar (save for Bottling Day)

These simple instructions are basic brewing procedures for this Northern Brewer extract beer kit; please refer to your starter kit instructions for specific instructions on use of equipment and common procedures such as siphoning, sanitizing, bottling, etc.

For more detailed extract brewing instructions, please visit [www.northernbrewer.com](http://www.northernbrewer.com)

## BEFORE YOU BEGIN ...

### MINIMUM REQUIREMENTS

- Homebrewing starter kit for brewing 5 gallon batches
- Boiling kettle of at least 3.5 gallons capacity
- A 5 gallon glass carboy, with bung and airlock, to use as a secondary fermenter
- Approximately two cases of either 12 oz or 22 oz pry-off style beer bottles

### UNPACK THE KIT

- Refrigerate the yeast upon arrival
- Locate the Kit Inventory (above) - this is the recipe for your beer, so keep it handy
- Doublecheck the box contents vs. the Kit Inventory
- Contact us immediately if you have any questions or concerns!

## PROCEDURE

### A FEW DAYS BEFORE BREWING DAY

1. Remove the liquid Wyeast pack from the refrigerator, and “smack” as shown on the back of the yeast package. Leave it in a warm place (70-80° F) to incubate until the pack begins to inflate. Allow at least 3 hours for inflation; some packs may take up to several days to show inflation. Do not brew with inactive yeast – we can replace the yeast, but not a batch that fails to ferment properly. If you are using dry yeast, no action is needed.

2. Prepare a yeast starter. Follow the Yeast Starter Kit instructions. Allow the starter to incubate for at least one day.

### ON BREWING DAY

3. Collect and heat 2.5 gallons of water.

4. For mail-order customers grains for extract kits come crushed by default, but if you requested uncrushed grains, crush them now. Pour crushed grain into supplied mesh bag and tie the open end in a knot. Steep for 20 minutes or until water reaches 170°F. Remove bag and discard.

5. Bring to a boil and add 5 lbs Amber DME. Remove the kettle from the burner and stir in the Amber DME.

6. Return wort to boil. The mixture is now called “wort”, the brewer’s term for unfermented beer.

- Add 0.75 oz Perle hops and boil for 60 minutes.

- Add 1 lb Corn Sugar at the end of the boil.

7. Cool the wort. When the 60-minute boil is finished, cool the wort as close to 64° F as rapidly as possible. Use a wort chiller, or put the kettle in an ice bath in your sink.

8. Sanitize fermenting equipment and yeast pack. While the wort cools, sanitize the fermenting equipment - fermenter, lid or stopper, fermentation lock, funnel, etc - along with the yeast pack and a pair of scissors.

9. Fill primary fermenter with 2 gallons of cold water, then pour in the cooled wort. Leave any thick sludge in the bottom of the kettle.

10. Add more cold water as needed to bring the volume to 5 gallons.

11. Aerate the wort. Seal the fermenter and rock back and forth to splash for a few minutes, or use an aeration system and diffusion stone.

12. Measure specific gravity of the wort with a hydrometer and record.

13. Add yeast once the temperature of the wort is as close to 64°F as possible. Use the sanitized scissors to cut off a corner of the yeast pack or take your yeast starter, and carefully pour the yeast into the primary fermenter.

14. Seal the fermenter. Add approximately 1 tablespoon of water to the sanitized fermentation lock. Insert the lock into rubber stopper or lid, and seal the fermenter.

15. Move the fermenter to a dark, quiet spot until fermentation begins.

### BEYOND BREWING DAY, WEEKS 1–2

16. Active fermentation begins. Within approximately 48 hours of Brewing Day, active fermentation will begin - there will be a cap of foam on the surface of the beer, the specific gravity as measured with a hydrometer will drop steadily, and you may see bubbles come through the fermentation lock. The optimum fermentation temperature for this beer is 45-68° F - move the fermenter to a warmer or cooler spot as needed.

17. Active fermentation ends. Approximately two weeks after brewing day, active fermentation will end. When the cap of foam falls back into the new beer, bubbling in the fermentation lock slows down or stops, and the specific gravity as measured with a hydrometer is stable, proceed to the next step.

### BEYOND BREWING DAY— SECONDARY FERMENTATION

18. Lagering. Slowly lower the temperature of the beer to as close to 35-40° F as your equipment allows. The best method is to lower the temperature by a couple of degrees each day until the target temperature is reached. Allow the beer to condition on the yeast at a cool temperature for 2-3 weeks after active fermentation has ceased.

### BOTTLING DAY—ABOUT 1.5 MONTHS AFTER BREWING DAY

19. Sanitize siphoning and bottling equipment.

20. Mix a priming solution (a measured amount of sugar dissolved in water to carbonate the bottled beer) of  $\frac{2}{3}$  cup priming sugar in 16 oz water. Bring the solution to a boil and pour into the bottling bucket.

21. Siphon beer into bottling bucket and mix with priming solution. Stir gently to mix—don’t splash.

22. Fill and cap bottles.

### 2 WEEKS AFTER BOTTLING DAY

23. Condition bottles at room temperature for 2 weeks. After this point, the bottles can be stored cool or cold.

24. Serving. Pour into a clean glass, being careful to leave the layer of sediment at the bottom of the bottle. Cheers!