

MUSTACHE ENVY BELGIAN STOUT

Official NORTHERN BREWER Instructional Document

Covered in the fine-laced hairs of a khaki-colored head lies this jet black, terribly handsome stout. A tangle of Belgian yeast dominates the nose, intertwining fruity esters and restrained phenolics. Mere whiskers of hop bitterness balance assertive roasted malt character. Its thick body and wooly mouthfeel warm the cheeks with substantial alcohol. Moderate effervescence combs through an oaky finish for a dense, distinguished, well-groomed pint.

This delicious Belgian stout is making a limited reappearance in support of the global men's health initiative us.Movember.com, which raises funds and awareness to tackle prostate and testicular cancer as well as mental health issues facing men. For every Mustache Envy kit purchased, Northern Brewer will donate \$5 to this worthy cause. Help fight cancer by brewing Envy and growing your 'stache.

O.G: 1.080 READY: 6 WEEKS

1-2 weeks primary, 2 weeks secondary, 2 weeks bottle conditioning

BOTTLE CONDITIONING & CELLARING: Drinkable when carbonated, will continue to evolve for months

KIT INVENTORY:

MAILLARD MALTS™ SPECIALTY GRAIN

- 0.5 lbs Belgian Aromatic
- 0.5 lbs English Roasted Barley
- 0.25 lbs Belgian Biscuit Malt
- 0.25 lbs Weyermann Carafa III

MAILLARD MALTS™ EXTRACTS & OTHER FERMENTABLES

- 6 lbs Gold malt syrup (60 min)
- 3 lbs Briess Dark dry malt extract (60 min)
- 1 lb Corn Sugar (60 min)

HOPTIMUS REX™ PREMIUM HOPS & OTHER FLAVORINGS

- 1 oz Northern Brewer hops (60 min)
- 1 oz UK Kent Goldings hops (60 min)
- 1 oz UK Kent Goldings hops (30 min)
- 3 oz French medium toast oak cubes (add to secondary)

DRY YEAST

- **SAFBREW ABBAYE**
Optimum temp: 59-68°F

LIQUID YEAST OPTIONS

- **OMEGA YEAST LABS OYL-020 BELGIAN ALE R**
Optimum temp: 65-75°F
- **WYEAST 1762 BELGIAN ABBEY II**
Optimum temp: 65-75°F

BEFORE YOU BEGIN ...

MINIMUM REQUIREMENTS

- Homebrewing starter kit for brewing 5 gallon batches
- Boiling kettle of at least 3.5 gallons capacity

- A 5 gallon glass carboy, with bung and airlock, to use as a secondary fermenter - If you do not have a secondary fermenter you may skip the secondary fermentation and add an additional week to primary fermentation before bottling

- Approximately two cases of either 12 oz or 22 oz pry-off style beer bottles

UNPACK THE KIT

- Refrigerate the yeast upon arrival
- Locate the Kit Inventory (above) - this is the recipe for your beer, so keep it handy
- Doublecheck the box contents vs. the Kit Inventory
- Contact us immediately if you have any questions or concerns!

PROCEDURE

A FEW DAYS BEFORE BREWING DAY

1. Remove the liquid yeast pack from the refrigerator. If using Wyeast, "smack" as shown on the back of the yeast package. Leave it in a warm place (70-80°F) to incubate until the pack begins to inflate. Allow at least 3 hours for inflation; some packs may take up to several days to show inflation. Do not brew with inactive yeast - we can replace the yeast, but not a batch that fails to ferment properly. If you are using dry yeast, no action is needed.

ON BREWING DAY

2. Collect and heat 2.5 gallons of water.
3. Pour crushed grain into supplied mesh bag and tie the open end in a knot. Steep for 20 minutes or until water reaches 170°F. Remove bag and discard.
4. Bring to a boil and add the 6 lbs Gold malt syrup, 1 lb Corn Sugar and 3 lbs Dark dry malt extract. Remove the kettle from the burner and stir in the Gold malt syrup, Corn Sugar, and Dark DME.
5. Return wort to boil. The mixture is now called "wort", the brewer's term for unfermented beer.
 - Add 1 oz Northern Brewer and 1 oz UK Kent Goldings hops and boil for 60 minutes.
 - Add 1 oz UK Kent Goldings hops 30 minutes from the end of the boil.

6. Cool the wort. When the 60-minute boil is finished, cool the wort to approximately 100°F as rapidly as possible. Use a wort chiller, or put the kettle in an ice bath in your sink.

7. Sanitize fermenting equipment and yeast pack. While the wort cools, sanitize the fermenting equipment - fermenter, lid or stopper, fermentation lock, funnel, etc - along with the yeast pack and a pair of scissors.

8. Fill primary fermenter with 2 gallons of cold water, then pour in the cooled wort. Leave any thick sludge in the bottom of the kettle.

9. Add more cold water as needed to bring the volume to 5 gallons.

10. Aerate the wort. Seal the fermenter and rock back and forth to splash for a few minutes, or use an aeration system and diffusion stone.

11. Measure specific gravity of the wort with a hydrometer and record.

12. Add yeast once the temperature of the wort is 78°F or lower (not warm to the touch). Use the sanitized scissors to cut off a corner of the yeast pack, and carefully pour the yeast into the primary fermenter.

13. Seal the fermenter. Add approximately 1 tablespoon of water to the sanitized fermentation lock. Insert the lock into rubber stopper or lid, and seal the fermenter.

14. Move the fermenter to a warm, dark, quiet spot until fermentation begins.

BEYOND BREWING DAY, WEEKS 1-2

15. Active fermentation begins. Within approximately 48 hours of Brewing Day, active fermentation will begin - there will be a cap of foam on the surface of the beer, the specific gravity as measured with a hydrometer will drop steadily, and you may see bubbles come through the fermentation lock. The optimum fermentation temperature for this beer is 65-75°F - move the fermenter to a warmer or cooler spot as needed.

16. Active fermentation ends. Approximately one week to two weeks after Brewing Day, active fermentation will end. When the cap of foam falls back into the new beer, bubbling in the fermentation lock slows down or stops, and the specific gravity as measured with a hydrometer is stable, proceed to the next step.

17. Optional - Transfer beer to secondary fermenter. Sanitize siphoning equipment and an airlock and carboy bung or stopper. Siphon the beer from the primary fermenter into the secondary. If not using a secondary, leave the beer in your primary fermenter.

BEYOND BREWING DAY— SECONDARY FERMENTATION

18. Secondary fermentation. Allow the beer to condition in the secondary fermenter for 2-4 weeks before proceeding with the next step. Timing now is somewhat flexible.

19. Add the oak cubes. Add 3 oz French medium toast oak cubes to the secondary fermenter 7-10 days before bottling day.

BOTTLING DAY—ABOUT 1 MONTH AFTER BREWING DAY

20. Sanitize siphoning and bottling equipment.

21. Mix a priming solution (a measured amount of sugar dissolved in water to carbonate the bottled beer). Use the following amounts, depending on which type of sugar you will use:

- Corn sugar (dextrose) $\frac{2}{3}$ cup in 16 oz water.
- Table sugar (sucrose) $\frac{5}{8}$ cup in 16 oz water.

Then bring the solution to a boil and pour into the bottling bucket.

22. Siphon beer into bottling bucket and mix with priming solution. Stir gently to mix, don't splash.

23. Fill and cap bottles.

1-2 WEEKS AFTER BOTTLING DAY

24. Condition bottles at room temperature for 1-2 weeks. After this point, the bottles can be stored cool or cold.

25. Serving. Pour into a clean glass, being careful to leave the layer of sediment at the bottom of the bottle. Cheers!