

SHIRLEY FURIOSO

Official NORTHERN BREWER Instructional Document

Modeled on a cult craft beer from the Twin Cities, this is the kind of American IPA that you break up with, then get back together with, then break up with again, and so on. The next thing you know you're pawning your TV to buy expensive designer beer cozies, but you still can't quit that brew: it's a mean character and you're attracted to danger. Go on, say you love it. A copper-colored ale with a hop lover's hop profile: bitter, herbal, floral, complex, and overstated. A hefty charge of caramel malt takes the edge off the alpha acids eating away at your cheeks while you savor it. There's no way this can end well, but right now it tastes so good you just don't care.

NOTE: THIS RECIPE IS CALIBRATED TO YIELD 5.5 GALLONS OF 1.062 WORT, TO ALLOW FOR VOLUME LOST IN THE BOIL KETTLE DUE TO THE LARGE AMOUNT OF HOPS.

- **O.G: 1.062** **READY: 6 WEEKS**

1-2 weeks primary, 2-4 weeks secondary, 1-2 weeks bottle conditioning

KIT INVENTORY:

MAILLARD MALTS™ SPECIALTY GRAIN

- 1 lb Belgian Cara 45
- 0.5 lbs Briess Caramel 60
- 0.125 lbs Simpsons Black Malt

MAILLARD MALTS™ EXTRACTS & OTHER FERMENTABLES

- 3.15 lbs Amber malt syrup (60 min)
- 6 lbs Gold malt syrup late addition (15 min)

HOPTIMUS REX™ PREMIUM HOPS & OTHER FLAVORINGS

- 1 oz Summit (60 min)
- 0.5 oz Ahtanum (20 min)
- 0.5 oz Amarillo (20 min)
- 0.5 oz Simcoe (20 min)
- 0.5 oz Ahtanum (10 min)
- 0.5 oz Amarillo (10 min)
- 0.5 oz Simcoe (10 min)
- 2 oz Simcoe (dry hop)
- 1 oz Amarillo (dry hop)

YEAST

- **WYEAST 1335 BRITISH ALE II.** Typical of British and Canadian ale fermentation profile with good flocculating and malty flavor characteristics, crisp finish, clean, fairly dry. Apparent attenuation: 73-76%. Flocculation: high. Optimum temp: 63-75° F.
- **DRY YEAST ALTERNATIVE:** Danstar Nottingham Ale Yeast. Optimum temp: 57-70° F.

These simple instructions are basic brewing procedures for this Northern Brewer extract beer kit; please refer to your starter kit instructions for specific instructions on use of equipment and common procedures such as siphoning, sanitizing, bottling, etc.

For more detailed extract brewing instructions, please visit www.northernbrewer.com

BEFORE YOU BEGIN ...

MINIMUM REQUIREMENTS

- Homebrewing starter kit for brewing 5 gallon batches
- Boiling kettle of at least 3.5 gallons capacity
- A 5 gallon glass carboy, with bung and airlock, to use as a secondary fermenter - If you do not have a secondary fermenter you may skip the secondary fermentation and add an additional week to primary fermentation before bottling
- Approximately two cases of either 12 oz or 22 oz pry-off style beer bottles

UNPACK THE KIT

- Refrigerate the yeast upon arrival
- Locate the Kit Inventory (above) - this is the recipe for your beer, so keep it handy
- Doublecheck the box contents vs. the Kit Inventory
- Contact us immediately if you have any questions or concerns!

PROCEDURE

A FEW DAYS BEFORE BREWING DAY

1. Remove the liquid Wyeast pack from the refrigerator, and "smack" as shown on the back of the yeast package. Leave it in a warm place (70-80° F) to incubate until the pack begins to inflate. Allow at least 3 hours for inflation; some packs may take up to several days to show inflation. Do not brew with inactive yeast - we can replace the yeast, but not a batch that fails to ferment properly. If you are using dry yeast, no action is needed.

ON BREWING DAY

2. Collect and heat 2.5 gallons of water.
3. For mail-order customers grains for extract kits come crushed by default, but if you requested uncrushed grains, crush them now. Pour crushed grain into supplied mesh bag and tie the open end in a knot. Steep for 20 minutes or until water reaches 170°F. Remove bag and discard.
4. Bring to a boil and add the 3.15 lbs Amber malt syrup. Remove the kettle from the burner and stir in the Amber malt syrup.
5. Return wort to boil. The mixture is now called "wort", the brewer's term for unfermented beer.

- Add 1 oz Summit hops and boil for 60 minutes.
- Add 0.5 oz Ahtanum, 0.5 oz Amarillo, and 0.5 oz Simcoe hops 20 minutes before the end of the boil.
- Add 6 lbs malt syrup 15 minutes before the end of the boil.
- Add 0.5 oz Ahtanum, 0.5 oz Amarillo, and 0.5 oz Simcoe hops 10 minutes before the end of the boil.

6. Cool the wort. When the 60-minute boil is finished, cool the wort to approximately 100° F as rapidly as possible. Use a wort chiller, or put the kettle in an ice bath in your sink.
7. Sanitize fermenting equipment and yeast pack. While the wort cools, sanitize the fermenting equipment - fermenter, lid or stopper, fermentation lock, funnel, etc - along with the yeast pack and a pair of scissors.

8. Fill primary fermenter with 2 gallons of cold water, then pour in the cooled wort. Leave any thick sludge in the bottom of the kettle.

9. Add more cold water as needed to bring the volume to 5 gallons.

10. Aerate the wort. Seal the fermenter and rock back and forth to splash for a few minutes, or use an aeration system and diffusion stone.

11. Measure specific gravity of the wort with a hydrometer and record.

12. Add yeast once the temperature of the wort is 78°F or lower (not warm to the touch). Use the sanitized scissors to cut off a corner of the yeast pack, and carefully pour the yeast into the primary fermenter.

13. Seal the fermenter. Add approximately 1 tablespoon of water to the sanitized fermentation lock. Insert the lock into rubber stopper or lid, and seal the fermenter.

14. Move the fermenter to a warm, dark, quiet spot until fermentation begins.

BEYOND BREWING DAY, WEEKS 1-2

15. Active fermentation begins. Within approximately 48 hours of Brewing Day, active fermentation will begin - there will be a cap of foam on the surface of the beer, the specific gravity as measured with a hydrometer will drop steadily, and you may see bubbles come through the fermentation lock. The optimum fermentation temperature for this beer is 63-75° F - move the fermenter to a warmer or cooler spot as needed.

16. Active fermentation ends. Approximately one week to two weeks after brewing day, active fermentation will end. When the cap of foam falls back into the new beer, bubbling in the fermentation lock slows down or stops, and the specific gravity as measured with a hydrometer is stable, proceed to the next step.

17. Transfer beer to secondary fermenter. Sanitize siphoning equipment and an airlock and carboy bung or stopper. Siphon the beer from the primary fermenter into the secondary.

BEYOND BREWING DAY— SECONDARY FERMENTATION

18. Secondary fermentation. Allow the beer to condition in the secondary fermenter for 2-4 weeks before proceeding with the next step. Timing now is somewhat flexible.

19. Add the dry hops. Add 2 oz Simcoe and 1 oz Amarillo hops to the secondary fermenter 1-2 weeks before bottling day.

BOTTLING DAY—ABOUT 1 MONTH AFTER BREWING DAY

20. Sanitize siphoning and bottling equipment.

21. Mix a priming solution (a measured amount of sugar dissolved in water to carbonate the bottled beer). Use the following amounts, depending on which type of sugar you will use:

- Corn sugar (dextrose) $\frac{2}{3}$ cup in 16 oz water.
- Table sugar (sucrose) $\frac{5}{8}$ cup in 16 oz water.

Then bring the solution to a boil and pour into the bottling bucket.

22. Siphon beer into bottling bucket and mix with priming solution. Stir gently to mix, don't splash.